

MIPAR™

Network License Activation Instructions


CLIENT SIDE

License Keys may be activated directly within MIPAR using the guided Activation Window.

This window appears after launching MIPAR if there are no active licenses. You may also access it in any app from Help > Activate License.

1. Allow Access to Server (允许访问服务器)

- Go to your License Manager's [Configuration Page](#).
- Click the **Access to Remote License Managers** tab.
- Check **Allow Access to Remote Licenses**.



2. Choose Search Type (选择搜索类型)

- Enter **Remote License Search Parameters**

Defines specific machines to search — must be used if access restrictions were set on server


Specify data as IP addresses (for example, 10.1.1.17),

Broadcast addresses (for example 10.1.1.255), or

machine names (for example, hklm001.ecomp.com)

Each entry must be on a separate line.

- Click **Submit** to apply any changes



SERVER SIDE

1.Start License Manager


- If you have not setup MIPAR on this system, double-click on **Start License Manager**.

2.Create System Fingerprint

- If you **HAVE NOT** setup MIPAR on this system
 - Launch the **RUS_MIPAR.exe** utility in the LicensePack
 - Click **Collect Information** and follow the prompts to save C2V file
- If you **HAVE** setup MIPAR on this system
 - Launch **MIPAR**
 - If Activation Window does not appear, go to Help > Activate License from any app
 - Click **Local**, then click **Save Fingerprint** and follow the prompts to save C2V file



3.Download License Key

- Go to the [License Key Download Page](#)
- Enter your emailed **Product Key** — click **Login**
- Click **Offline Activation** in the top right corner
- Click the “...” button next to “Upload C2V”
- Choose the C2V file you created
- Click **Generate**
- Once generated, click **Download V2C File**



4.Activate License Key

- Go to your License Manager’s [Activation Page](#)
- Click **Choose File** and choose the V2C file
- Click **Apply File**. Your license key is now activated!



5.Configure Network Access

- Click **Configuration** on the left sidebar

Allow Access from Remote Clients

- Click the **Access from Remote Clients** tab
- Check **Allow Access from Remote Clients**
- Make sure **Network Visibility** (on the **Network** tab) is set to **All Network Adapters**
- Click **Submit** to apply any changes



Access Restrictions (optional)

- Click the **Access from Remote Clients** tab
- Define the restrictions

that will be imposed on remote machines accessing this License Server. Enter data in the



following format: `allow=[item]` and/or `deny=[item]`, where item is an IP address or machine name. IP addresses can include "*" or a range of addresses allow or deny multiple addresses. The value of item can also be all or none. Each entry must be on a separate line. The entries are evaluated in the order in which they are specified.

For example, item can be:

10.24.2.18 a single address

10.24.2.10-50 range of addresses (only 4th number may be a range)

10.24.2.* class C subnet

10.24.*.* class B subnet

10.*.*.* class A subnet

10.24.2.0/24 subnet, number of mask bits specified

- Click **Submit** to apply any changes

We thank you sincerely for being a MIPAR user!

Please email us with any needs or questions.